# Windows 7 - Static DNS setup

## Windows 7 - Static DNS setup Aim of this article:

This article provides instructions on configuring Windows 7 to use statically assigned DNS server addresses.

### Setup:

Begin by clicking Windows Logo > **Control Panel**.



Network and Internet View network status and tasks Choose homegroup and sharing options



Hardware and Sound

View devices and printers Add a device

### Click Network and Internet.



Copyright © 2018 SUNNY-NET, Ltd. All rights reserved.

Connection		
IPv4 Connectiv	vity:	Internet
IPv6 Connectiv	rity:	No network access
Media State:		Enabled
Duration:		00:01:23
Speed:		100.0 Mbps
Details	)	
Details	Sent —	Received
Details Activity Bytes:	Sent —	Received

Click the name of the connection you wish the edit, to the right of **Connections**.

Click **Properties**. You will then be presented with the following window.

Connect using:		
Marvell Yuko	n 88E8053 PCI-E Gigabit Eth	ernet Controller
		Configure
This connection use:	s the following items:	
🗹 🏪 Client for Mic	rosoft Networks	2
🗹 🚚 Virtual PC Ne	etwork Filter Driver	
🗹 🛃 QoS Packet	Scheduler	
File and Prin	ter Sharing for Microsoft Net	works
🗹 🔺 Internet Prote	ocol Version 6 (TCP/IPv6)	
🗹 🔟 Internet Prote	ocol Version 4 (TCP/IPv4)	
🗹 📥 Link-Layer T	opology Discovery Mapper	I/O Driver
🗹 🔺 Link-Layer T	opology Discovery Respon	ider
	Uninstall	Properties
Install		·
Description		
Description Transmission Cor area network prot	ntrol Protocol/Internet Protoc	ol. The default wide cation across
Description Transmission Col area network prot diverse interconn	ntrol Protocol/Internet Protoco ocol that provides communi ected networks.	ol. The default wide cation across

Select Internet Protocol Version 4 (TCP/IPv4) and click Properties.

Copyright © 2018 SUNNY-NET, Ltd. All rights reserved.

#### SUNNY-NET Static DNS Setup Instructions for Windows 7

erierai	Alternate Configuration				
You car this cap for the	n get IP settings assigned a pability. Otherwise, you nee appropriate IP settings.	utomatically if y d to ask your n	our ne etwor	etwork su k administ	pports rator
0	btain an IP address automa	tically			
OU	se the following IP address:				
IP a	ddress:		+		
Subr	net mask:				
Defa	ult gateway:		5		
00	btain DNS server address a	utomatically			
() U:	e the following DNS server	addresses:			
Pref	erred DNS server:	209 · 58	· 18	30 · 215	
Alter	nate DNS server:	198 . 7	• 6	2 · 199	
V	alidate settings upon exit			Advan	ced

Click the radio button next to **Use the following DNS server addresses:**. This will allow you to enter the DNS server addresses.

The DNS addresses are as follows:

Preferred DNS server: 209.58.180.215

Alternate DNS server: 198.7.62.199

Click **OK** on each of the windows and close the Control Panel. Your computer is now configured to use statically assigned DNS server addresses.